# Installing the Geography Learning System from the GLS zip file

# Richard C. Brandt Darbick Instructional Software Systems 800-311-9241 and r.c.brandt@worldnet.att.net

### November 15, 1999

### Contents

1

2

3

4

		three of them below. The first is for the case you already have PKZIP installed on your system. The
Introduction	1	second is for the case where you do not have PKZIP and will use unzip.exe instead. In either case, I
CASE 1. PKZIP is installed	1	recommend you print this file before proceeding. If you are using either Netscape or Internet Explorer,
CASE 2. PKZIP is not available	2	open install.html and print it before proceeding or if you have Adobe Acrobat Reader open
CASE 3. PKZIP is not available and		install.pdf and print it. The third is for the case of poor phone lines; the largest file transferred is
phone lines are poor	2	1.44 Mb instead of 7.5 Mb.

3

### 1 Introduction

5 Problems

To install the Geography Learning System from the GLS zip file you will need one to three files (eight for poor phone lines):

- gls.zip (about 7.5 Mb) or for poor phone lines: glsdisk1.zip, glsdisk2.zip, glsdisk3.zip, glsdisk4.zip, glsdisk5.zip, and glsdisk6.zip (about 1.44 Mb apiece)
- unzip.exe (about 0.1 Mb optional)
- install.html (about 10 Kb optional) or install.pdf (about 75 Kb optional)

Unzip.exe is required only if you do not have PKZIP installed on your system. Install.html is required only if you are using FTP for the transfer. Install.pdf is required only if you have neither Netscape or Internet Explorer but you do have Adobe Acrobat Reader.

### 2 CASE 1. PKZIP is installed

There are many ways to install GLS; I describe

Download gls.zip and install.html (if not already printed) to a temporary folder. It can be C:\TMP, E:\TMP, or whatever. The download of gls.zip may take a long time since gls.exe is about 7.5 Mb in size.

- Start Windows Explorer and first connect to the temporary folder in which you have placed gls.zip and possibly install.html. If you have not printed either install.html or install.pdf, double click on the appropriate one, starting either your browser or Acrobat Reader and print it. Then exit your browser or Acrobat Reader and return to Windows Explorer.
- Double click on gls.zip starting PKZIP. A list of the files in gls.zip will appear along with the PKZIP menu items.
- Move the cursor to the PKZIP menu item "Unzip" and click on the drop-down menu item "Extract files." The Extract Window will appear with the All File radio button marked.

- Click on the Extract button. This will extract all files into the current folder.
- Click on Done and then Exit drop down item in the File menu to leave PKZIP and return to Window Explorer. The right window in Windows Explorer will show the extracted files.
- Double click on setup.exe to start the installation. From here on the installation is normal; follow the printed notes from install.html or install.pdf.

### 3 CASE 2. PKZIP is not available

Download unzip.exe, gls.zip and install.html (if not already printed) to a temporary folder. It can be C:\TMP, E:\TMP, or whatever. The download of gls.zip may take a long time since gls.zip is about 7.5 Mb in size.

- From the Program Menu start MS-DOS (Windows 95) or the Command Prompt (Windows NT).
- Connect to the folder in which you placed the files. For example, if you placed them in C:\TMP, enter:

cd C:\TMP

If you have not printed either install.html or install.pdf, print it now by starting the appropriate program. If the the file is install.html enter

install.html

If the file is install.pdf, enter

install.pdf

Use your browser or Acrobat Reader as appropriate to print the installation instructions, exit, and return to the prompt line.

• Unzip gls.zip using unzip.exe by entering:

unzip gls

• Start setup.exe by entering

#### setup

From here on the installation is normal; follow the printed notes from install.html or install.pdf.

# 4 CASE 3. PKZIP is not available and phone lines are poor

Download unzip.exe, glsdisk1.zip, glsdisk2.zip, glsdisk3.zip, glsdisk4.zip, glsdisk5.zip, glsdisk6.zip and install.html (if not already printed) to a temporary folder. It can be C:\TMP, E:\TMP, or whatever. The process of downloading the various glsdisk zip files may take a long time since each file is about 1.44 Mb in size.

- From the Program Menu start MS-DOS (Windows 95) or the Command Prompt (Windows NT).
- Connect to the folder in which you placed the files. For example, if you placed them in C:\TMP, enter:

cd C:\TMP

If you have not printed either install.html or install.pdf, print it now by starting the appropriate program. If the the file is install.html enter

install.html

If the file is install.pdf, enter

install.pdf

Use your browser or Acrobat Reader as appropriate to print the installation instructions, exit, and return to the prompt line.

• Unzip glsdisk zip files using unzip.exe by entering:

unzip glsdisk1 unzip glsdisk2 unzip glsdisk3 unzip glsdisk4 unzip glsdisk5 unzip glsdisk6 This will create 6 subfolders labeled disk1, disk2, disk3, disk4, disk5, and disk6.

• Start setup.exe by entering

### disk1\setup

From here on the installation is normal; follow the printed notes from install.html or install.pdf. The authorization file, if present, is in the disk6 folder.

### 5 Problems

If you have problems, call me at 800-311-9241 or email me, r.c.brandt@worldnet.att.net, and I will try to help.